



Software Vulnerability Manager (On-Premises Edition)

Virtual Appliance Installation Guide

Legal Information

Book Name: Software Vulnerability Manager (On-Premises Edition) Virtual Appliance Installation Guide
Part Number: SVMOPe-MAY2020-IGVA00
Product Release Date: May 2020

Copyright Notice

Copyright © 2020 Flexera

This publication contains proprietary and confidential information and creative works owned by Flexera and its licensors, if any. Any use, copying, publication, distribution, display, modification, or transmission of such publication in whole or in part in any form or by any means without the prior express written permission of Flexera is strictly prohibited. Except where expressly provided by Flexera in writing, possession of this publication shall not be construed to confer any license or rights under any Flexera intellectual property rights, whether by estoppel, implication, or otherwise.

All copies of the technology and related information, if allowed by Flexera, must display this notice of copyright and ownership in full.

Intellectual Property

For a list of trademarks and patents that are owned by Flexera, see <https://www.flexera.com/legal/intellectual-property.html>. All other brand and product names mentioned in Flexera products, product documentation, and marketing materials are the trademarks and registered trademarks of their respective owners.

Restricted Rights Legend

The Software is commercial computer software. If the user or licensee of the Software is an agency, department, or other entity of the United States Government, the use, duplication, reproduction, release, modification, disclosure, or transfer of the Software, or any related documentation of any kind, including technical data and manuals, is restricted by a license agreement or by the terms of this Agreement in accordance with Federal Acquisition Regulation 12.212 for civilian purposes and Defense Federal Acquisition Regulation Supplement 227.7202 for military purposes. The Software was developed fully at private expense. All other use is prohibited.

Contents

1	Software Vulnerability Manager (On-Premises Edition) Virtual Appliance Installation Guide	5
	Product Support Resources	7
	Contact Us	8
2	Installing Software Vulnerability Manager Ubuntu OS	9
	Initial Configuration	10
	Configure Your Console Data	11
	Configure Your Time Zone Data	11
	Change Your Administrator Password	12
	Network Configuration	12
	Customer Information	13
	Server Configuration	14
	Create Server Certificate	15
	Disk Initialization	15
	Database Configuration	16
	Configure Your Maria DB Server (Optional)	16
	Proxy Configuration	17
	Email and SMS Settings	17
	Software Updates	18
	LDAP Configuration	19
3	Installing Software Vulnerability Manager CentOS	21
	Initial Configuration	22
	Configure Your Time Zone	23
	Configure Your Keyboard Layout	24
	Configure Your System Language	25
	Change Your Administrator Password	25
	Network Configuration	26

- Customer Information..... 27**
- Server Configuration..... 28**
 - Create Server Certificate 29
- Disk Initialization..... 29**
- Database Configuration 30**
- Proxy Configuration 30**
- Email and SMS Settings..... 31**
- Software Updates 31**
- LDAP Configuration 32**
- A Appendix A - CentOS VA Migration from Ubuntu VA 33**
 - Actions on Ubuntu Virtual Appliance..... 33
 - Actions on CentOS Virtual Appliance..... 34
 - Migration Steps 35

Software Vulnerability Manager (On-Premises Edition) Virtual Appliance Installation Guide

Software Vulnerability Manager is a revolutionary tool that simplifies the troublesome area of identifying vulnerable programs and patching them. Software Vulnerability Manager Virtual Appliance provides you with an easy way to deploy and configure Software Vulnerability Manager without the need install and configure a Linux server from scratch. The VA is designed to be easy to deploy and require minimal maintenance.

- If the appliance is based on Ubuntu Server LTS 14.04, then it requires VMware vSphere 5.0+ with vSphere Client to deploy and run the Virtual Appliance. Deployment on VMWare and ESX is also supported.
- If the appliance is based on CentOS, deployment on VMWare and HyperV virtualization platforms is also supported.

By scanning the network, organizations can effectively protect their corporate IT infrastructure against the threat posed by unpatched vulnerabilities:


- Non-intrusive authenticated vulnerability and patch scanning
- Covers programs and plug-ins from thousands of vendors
- Unprecedented accuracy, no more false positives
- Reports security status for each program
- Reports criticality rating for each insecure program
- Reports end-of-life programs
- Identifies missing patches
- Automated patch repackaging
- Integration with WSUS for easy patch distribution
- Integration with System Center Configuration Manager for extensive patch management

The Software Vulnerability Manager (On-Premises Edition) Virtual Appliance Installation Guide is organized in the following sections:

Table 1-1 • Software Vulnerability Manager On-Premises Edition Virtual Appliance Installation Guide

Topic	Content
Installing Software Vulnerability Manager Ubuntu OS	<p>The following topics appear in the order that they appear in the installation procedure.</p> <ul style="list-style-type: none"> ● Initial Configuration ● Network Configuration ● Customer Information ● Server Configuration ● Disk Initialization ● Database Configuration ● Configure Your Maria DB Server (Optional) ● Proxy Configuration ● Email and SMS Settings ● Software Updates ● LDAP Configuration
Installing Software Vulnerability Manager CentOS	<p>The following topics appear in the order that they appear in the installation procedure.</p> <ul style="list-style-type: none"> ● Initial Configuration ● Network Configuration ● Customer Information ● Server Configuration ● Disk Initialization ● Database Configuration ● Proxy Configuration ● Email and SMS Settings ● Software Updates ● LDAP Configuration

Table 1-1 • Software Vulnerability Manager On-Premises Edition Virtual Appliance Installation Guide

Topic	Content
Appendix A - CentOS VA Migration from Ubuntu VA	<p>Explains Migration from Ubuntu Virtual Appliance to CentOS Virtual Appliance</p> <ul style="list-style-type: none">• Actions on Ubuntu Virtual Appliance• Actions on CentOS Virtual Appliance• Migration Steps  <p>Note • Flexera highly recommends to use the CentOS Virtual Appliance to deploy the Software Vulnerability Manager.</p>

Product Support Resources

The following resources are available to assist you with using this product:

- [Flexera Product Documentation](#)
- [Flexera Community](#)
- [Flexera Learning Center](#)
- [Flexera Support](#)

Flexera Product Documentation

You can find documentation for all Flexera products on the [Flexera Product Documentation](#) site:

<https://docs.flexera.com>

Flexera Community

On the [Flexera Community](#) site, you can quickly find answers to your questions by searching content from other customers, product experts, and thought leaders. You can also post questions on discussion forums for experts to answer. For each of Flexera's product solutions, you can access forums, blog posts, and knowledge base articles.

<https://community.flexera.com>

Flexera Learning Center

Flexera offers a variety of training courses—both instructor-led and online—to help you understand how to quickly get the most out of your Flexera products. The Flexera Learning Center offers free, self-guided, online training classes. You can also choose to participate in structured classroom training delivered as public classes. You can find a complete list of both online content and public instructor-led training in the Learning Center.

<https://learn.flexera.com>

Flexera Support

For customers who have purchased a maintenance contract for their product(s), you can submit a support case or check the status of an existing case by making selections on the **Get Support** menu of the Flexera Community.

<https://community.flexera.com>

Contact Us

Flexera is headquartered in Itasca, Illinois, and has offices worldwide. To contact us or to learn more about our products, visit our website at:

<http://www.flexera.com>


You can also follow us on social media:

- [Twitter](#)
- [Facebook](#)
- [LinkedIn](#)
- [YouTube](#)
- [Instagram](#)

Installing Software Vulnerability Manager Ubuntu OS

The following steps appear in the order that they appear in the installation procedure. You can use the arrow and Page Up/Down keys to navigate, press ESC to go back or F2 to open an administrator shell.

- Initial Configuration
- Network Configuration
- Customer Information
- Server Configuration
- Disk Initialization
- Database Configuration
- Configure Your Maria DB Server (Optional)
- Proxy Configuration
- Email and SMS Settings
- Software Updates
- LDAP Configuration





Important • Note the below following recommendations on Virtual Appliance:

- Flexera highly recommends to use the CentOS Virtual Appliance to deploy the Software Vulnerability Manager.
- To migrate from the Ubuntu Virtual Appliance to the CentOS Virtual Appliance, see [Appendix A - CentOS VA Migration from Ubuntu VA](#).


Initial Configuration

To start the configuration, login to your Software Vulnerability Manager server as root and enter the default password (flexera).

```
Ubuntu 14.04.3 LTS csi-server tty1
csi-server login: root
Password: _
```


The Initial Configuration screen will appear. Click Begin to start configuring the Software Vulnerability Manager Virtual Appliance for the following.

- [Configure Your Console Data](#)
- [Configure Your Time Zone Data](#)
- [Change Your Administrator Password](#)




Configure Your Console Data

Select the policy you want to use for handling keymaps and click OK.




Configure Your Time Zone Data

Select your geographic area from the list and click OK. You will then be presented with a list of cities representing the time zones in which they are located.



Change Your Administrator Password


Enter and confirm a new root account password for the Ubuntu Linux install on the VA and click **Next**.



Network Configuration

Choose the network configuration method to use and click **Next** to configure the following.

- Automatic (DHCP) Network Configuration
- Manual (Static) Network Connection
- Do Nothing




Automatic (DHCP) Network Configuration

If you selected **Automatic (DHCP)** in the previous step, no further action is required.

Manual (Static) Network Connection

If you selected **Manual (static)** in the previous step you must enter the required details and click **Save**.




The image shows a terminal window titled "Static Network Configuration". It contains five input fields for network settings: "IP address:", "Netmask:", "Gateway:", "Search domain(s):", and "Nameserver(s):". Each field is represented by a blue rectangular box. At the bottom of the window, there are two red buttons with white text: "Back" on the left and "Save" on the right.

Do Nothing

If you selected **Do nothing** in the previous step no further action is required.

Customer Information

Enter the name of your company, your Customer ID number that was supplied by Flexera and click **Save**.




The image shows a terminal window titled "Customer Information". It contains two input fields: "Company name:" and "Customer ID:". Each field is represented by a blue rectangular box. At the bottom of the window, there are two red buttons with white text: "Previous" on the left and "Next" on the right.

Server Configuration

Enter your Server Address, which can be a fully qualified domain name or an IP address, and click Next to [Create Server Certificate](#).



Note • This needs to match the URL that will be used to access the server via HTTP/HTTPS.



The screenshot shows a window titled "Server Configuration" with a grey background and a blue border. At the top, the title "Server Configuration" is displayed in red. Below the title, there is a text field labeled "Server Address:" containing the IP address "192.168.36.231". Below this, there is a checkbox labeled "Use SSL:" which is currently unchecked. A note below the checkbox states: "Server address can be a fully qualified domain name or an IP address." At the bottom of the window, there are two red buttons: "Previous" on the left and "Next" on the right.

Create Server Certificate

Enter your Domain Name, Company Name, Administration Email and Certificate Validity (years) and click Create Certificate.

This generates a self-signed certificate. It is necessary to distribute the certificate to all hosts running the UI, System Center Plugin, Daemon and agents. Currently the public certificate can be recovered either by copying it from inside the VA (it is saved as /etc/pki/tls/certs/) or by exporting it from Internet Explorer.

Create Server Certificate

Domain Name: 192.168.36.231
 Company Name: QA
 Administrative Email: admin@192.168.36.231
 Certificate Validity (years): 10

Back Create Certificate

Disk Initialization

Click Initialize Disks to partition your drives to ensure that you have enough disk space for the Software Vulnerability Manager Virtual Appliance.

When completed, click Next.

Disk Initialization


	Device	Size	Mount Point	Status
Root	/dev/sda	100.0 GiB	/	Mounted
Database	/dev/sdc	50.0 GiB	/var/lib/mysql	Uninitialized
Spool	/dev/sdd	50.0 GiB	/var/spool/csi	Uninitialized
Swap	/dev/sdb	4.0 GiB	none	Uninitialized

System disks need to be initialized.
 This operation will be performed only once.

Previous Initialize Disks

Database Configuration

Enter the Host, Username and Password details and then click Next.




The screenshot shows a window titled "Database Configuration". It contains three input fields: "Host:" with the value "localhost", "Username:" with the value "root", and "Password:" with masked characters "*****". Below these fields are two red buttons: "Back" and "Save".

Configure Your Maria DB Server (Optional)

Enter a new password for your MariaDB administrative root server (optional) and click OK. You will be asked to repeat the password.


When completed, click Ok.



The screenshot shows a window titled "Configuring mariadb-server-5.5". It contains the following text: "While not mandatory, it is highly recommended that you set a password for the MariaDB administrative 'root' user." followed by "If this field is left blank, the password will not be changed." Below this is the prompt "New password for the MariaDB 'root' user:" followed by a single-line text input field. At the bottom center is a button labeled "<Ok>".

Proxy Configuration


If your network uses a proxy to connect to the Internet, you can select Use Proxy, enter the Host, Port, Username and Password details and then click Next.



The image shows a 'Proxy Configuration' dialog box with a blue border. At the top, the title 'Proxy Configuration' is in red. Below it, there is a 'Use Proxy:' label followed by a checkbox that is currently checked. Underneath, there are four input fields labeled 'Host:', 'Port:', 'Username:', and 'Password:'. At the bottom, there are two red buttons labeled 'Previous' and 'Next'.

Email and SMS Settings


Enter the Email and SMS notification details and click **Next**.




The image shows an 'Email and SMS Settings' dialog box with a blue border. At the top, the title 'Email and SMS Settings' is in red. Below it, there are three input fields: 'Reply Email:' with the value 'admin@192.168.36.231', 'No-reply Email:' with the value 'no-reply@192.168.36.231', and 'SMTP Relay Server:'. Below these, there is an 'SMS Notifications:' label followed by a checkbox that is currently unchecked. At the bottom, there are two red buttons labeled 'Previous' and 'Next'.

Software Updates

Enable automatic software updates to check for, and install, security updates on a daily basis.



You will be informed of all available security updates and given the option to **Update now** or **Skip** them.




LDAP Configuration

Before configuring LDAP support you will need the following:

- The LDAP URL for your LDAP server
- The Base DN for the point in the directory where user-lookups will be made (the Base DN must contain at least one user account)
- The LDAP UID attribute that the usernames will be compared to
- The Bind DN for user-lookups or, alternatively, existing support for anonymous bind lookups


Select **Use LDAP**, enter the **LDAP Host URL**, **LDAP Base DN**, **UID Attribute**, and Bind details and then click **Save**.

A screenshot of the 'LDAP Configuration' dialog box. The dialog has a title bar with the text 'LDAP Configuration'. Inside, there is a section 'Use LDAP:' with a radio button that is currently selected. Below this, there are three input fields: 'LDAP Host URL:', 'LDAP Base DN:', and 'UID Attribute:'. Further down, there is a section 'Anonymous Bind:' with a radio button that is currently selected. Below this, there are two input fields: 'Bind DN:' and 'Bind Password:'. At the bottom of the dialog, there are two red buttons: 'Back' and 'Save'.

Installing Software Vulnerability Manager CentOS

The following steps appear in the order that they appear in the installation procedure. You can use the arrow and Page Up/Down keys to navigate, press ESC to go back or F2 to open an administrator shell.

- Initial Configuration
- Network Configuration
- Customer Information
- Server Configuration
- Disk Initialization
- Database Configuration
- Proxy Configuration
- Email and SMS Settings
- Software Updates
- LDAP Configuration




Initial Configuration

To start the configuration, login to your Software Vulnerability Manager 2019 server as root and enter the default password (flexera).

```
CentOS Linux 7 (Core)  
Kernel 3.10.0-957.12.1.el7.x86_64 on an  
  
localhost login: root  
Password: _
```

The Initial Configuration screen will appear. Click Begin to start configuring the Software Vulnerability Manager 2019 Virtual Appliance for the following.

- [Configure Your Time Zone](#)
- [Configure Your Keyboard Layout](#)
- [Configure Your System Language](#)



Configure Your Time Zone

Select your time zone from the list and click **Save**

Time Zone Locale


Pacific/Majuro
Pacific/Marquesas
Pacific/Midway
Pacific/Nauru
Pacific/Niue
Pacific/Norfolk
Pacific/Noumea
Pacific/Pago_Pago
Pacific/Palau
Pacific/Pitcairn
Pacific/Pohnpei
Pacific/Port_Moresby
Pacific/Rarotonga
Pacific/Saipan
Pacific/Tahiti
Pacific/Tarawa
Pacific/Tongatapu
Pacific/Wake
Pacific/Wallis
UTC

Save

Back

Configure Your Keyboard Layout

Select your keyboard layout from the list and click **Save**.




Keyboard Layout

- tr_q-latin5
- tralt
- trf
- trf-fgG1od
- trq
- ttwin_alt-UTF-8
- ttwin_cp1k-UTF-8
- ttwin_ct_sh-UTF-8
- ttwin_ctrl-UTF-8
- tw
- tw-indigenous
- tw-saisiyat
- ua
- ua-cp1251
- ua-utf
- ua-utf-ws
- ua-ws
- uk
- unicode
- us**

Save **Back**

Configure Your System Language


Select your system language from the list and click **Save**.



The image shows a window titled "System Language" with a list of language and locale options. The options are: en_IE.iso885915@euro, en_IE.utf8, en_IE@euro, en_IN, en_IN.utf8, en_NG, en_NG.utf8, en_NZ, en_NZ.iso88591, en_NZ.utf8, en_PH, en_PH.iso88591, en_PH.utf8, en_SG, en_SG.iso88591, en_SG.utf8, en_US, en_US.iso88591, en_US.iso885915, and en_US.utf8. The option "en_US.utf8" is highlighted with a red bar. At the bottom of the window, there are two red buttons: "Save" and "Back".

Change Your Administrator Password

Enter and confirm a new root account password for the CentOS Linux install on the Virtual Appliance and click Next.




The image shows a window titled "Change Administrator Password". It contains two input fields: "New password:" and "Confirm password:". Both fields are filled with asterisks (*****). Below the input fields, there are two red buttons: "Previous" and "Next".

Network Configuration

Choose the network configuration method to use and click Next to configure the following.

- Automatic (DHCP) Network Configuration
- Manual (Static) Network Connection
- Do Nothing




Note • To select any network configuration method, use **Space Bar** in the key board

Automatic (DHCP) Network Configuration

If you selected **Automatic (DHCP)** in the previous step no further action is required.

Manual (Static) Network Connection

If you selected **Manual (static)** in the previous step you must enter the required details and click **Save**.




The image shows a terminal window titled "Static Network Configuration". It contains five input fields for network settings: "IP address:", "Netmask:", "Gateway:", "Search domain(s):", and "Nameserver(s):". Each field is represented by a blue rectangular box. At the bottom of the window, there are two red buttons with white text: "Back" on the left and "Save" on the right.

Do Nothing

If you selected **Do nothing** in the previous step no further action is required.

Customer Information

Enter the name of your company, your Customer ID number that was supplied by Flexera and click **Save**.



The image shows a terminal window titled "Customer Information". It contains two input fields: "Company name:" and "Customer ID:". Each field is represented by a blue rectangular box. At the bottom of the window, there are two red buttons with white text: "Previous" on the left and "Next" on the right.

Server Configuration

Enter your Server Address, which can be a fully qualified domain name or an IP address, and click Next to [Create Server Certificate](#).



Note • This needs to match the URL that will be used to access the server via HTTP/HTTPS.

Server Configuration

Server Address: 10.80.130.22

Use SSL: ☒

Server address can be a fully qualified domain name or an IP address.

Previous

Next

Create Server Certificate

Enter your **Domain Name**, **Company Name**, **Administration Email** and **Certificate Validity (years)** and click **Create Certificate**.

This generates a self-signed certificate. It is necessary to distribute the certificate to all hosts running the UI, System Center Plugin, Daemon and agents. Currently the public certificate can be recovered either by copying it from inside the Virtual Appliance (it is saved as /etc/pki/tls/certs/) or by exporting it from Internet Explorer.

Create Server Certificate

Domain Name: svm.local

Company Name: Company

Administrative Email: admin@

Certificate Validity (years): 10

Certificate passphrase (optional):

Back Create Certificate

Disk Initialization

Click Initialize Disks to partition your drives to ensure that you have enough disk space for the Software Vulnerability Manager 2019 Virtual Appliance.

When completed, click **Next**.


Disk Information

	Device	Size	Mount Point	Status
Root	/dev/sda	500.0 GiB	/	Mounted
Database	/dev/mappe	120.0 GiB	/var/lib/mysql	Mounted
Spool	/dev/mappe	121.0 GiB	/var/spool/csi	Mounted
Swap	/dev/sda3	49.0 GiB	none	Mounted

Next

Database Configuration


Enter the **Host**, **Username** and **Password** details and then click **Next**.



The image shows a 'Database Configuration' window with a title bar. Inside, there are four text input fields: 'Host:' with 'localhost', 'Username:' with 'root', 'Password:', and 'Confirm Password:'. At the bottom, there are two red buttons labeled 'Previous' and 'Next'.

Proxy Configuration

If your network uses a proxy to connect to the Internet, you can select **Use Proxy**, enter the **Host**, **Port**, **Username** and **Password** details and then click **Next**.



The image shows a 'Proxy Configuration' window with a title bar. It features a 'Use Proxy:' checkbox which is currently unchecked. Below this are four text input fields: 'Host:', 'Port:', 'Username:', and 'Password:'. At the bottom, there are two red buttons labeled 'Previous' and 'Next'.

Email and SMS Settings


Enter the Email and SMS notification details and click **Next**.



The screenshot shows a configuration window titled "Email and SMS Settings". It contains three text input fields: "Reply Email:" with the value "admin@10.20.151.117", "No-reply Email:" with the value "no-reply@10.20.151.117", and "SMTP Relay Server:" which is empty. Below these fields is a checkbox labeled "SMS Notifications:" which is currently unchecked. At the bottom of the window are two red buttons: "Previous" on the left and "Next" on the right.


Software Updates

Enable automatic software updates to check for, and install, security updates on a daily basis.



The screenshot shows a configuration window titled "Software Updates". It features a checkbox labeled "Automatic Software Updates:" which is checked. Below this, a text block states: "When automatic software updates are enabled the appliance fetches and installs security updates daily." At the bottom of the window are three red buttons: "Previous" on the left, "Check now" in the center, and "Next" on the right.

Enter customer area **User Name** and **Password**, click **Download and install latest RPM**.




The screenshot shows a dialog box titled "Login and Auto Update". It contains two input fields: "User Name:" and "Password:". Below these fields is a URL: "URL: https://ca.secunia.com/download/". At the bottom of the dialog, there are two buttons: "Back" and "Login and Auto Update".

LDAP Configuration

Before configuring LDAP support you will need the following:

- The LDAP URL for your LDAP server
- The Base DN for the point in the directory where user-lookups will be made (the Base DN must contain at least one user account)
- The LDAP UID attribute that the usernames will be compared to
- The Bind DN for user-lookups or, alternatively, existing support for anonymous bind lookups

Select **Use LDAP**, enter the **LDAP Host URL**, **LDAP Base DN**, **UID Attribute**, and Bind details and then click **Save**.



The screenshot shows a dialog box titled "LDAP Configuration". It contains a section "Use LDAP:" with a dropdown menu showing "[*]". Below this are three input fields: "LDAP Host URL:", "LDAP Base DN:", and "UID Attribute:". There is also a section "Anonymous Bind:" with a dropdown menu showing "[*]". Below this are two input fields: "Bind DN:" and "Bind Password:". At the bottom of the dialog, there are two buttons: "Previous" and "Next".



Appendix A - CentOS VA Migration from Ubuntu VA

Migration from Ubuntu Virtual Appliance to CentOS Virtual Appliance includes the following steps:

- [Actions on Ubuntu Virtual Appliance](#)
- [Actions on CentOS Virtual Appliance](#)
- [Migration Steps](#)



Important • Before starting the migration, make sure the `vuLn_track` database is synced.

Actions on Ubuntu Virtual Appliance

To migrate to the CentOS Virtual Appliance, follow the below preparatory steps in Ubuntu Virtual Appliance.



Task

To migrate to the CentOS Virtual Appliance:

1. Create admin migration user using the below command:

```
GRANT ALL PRIVILEGES ON *.* TO 'mig_admin'@'%' IDENTIFIED BY 'MIG_ADMIN' WITH GRANT OPTION;  
FLUSH PRIVILEGES;
```

2. **Stop the services** using the below commands:

```
service scandaemon stop  
service sgdaemon stop  
service haproxy stop
```

3. Connect to the database and truncate `nsi_result` table from all the private databases for fast completion:

```
TRUNCATE ca_<custid>.nsi_result;(delete from all partitions).  
TRUNCATE ca.scan_queue; (Ideally no entries, when scan is not pending)
```

4. Check for enough disk space, tmp space, free RAM before proceeding.
5. Make sure that Apache service is running in both the servers.

Actions on CentOS Virtual Appliance

To migrate from the Ubuntu Virtual Appliance, follow the below preparatory steps in CentOS Virtual Appliance.



Task

To migrate from the Ubuntu Virtual Appliance:

1. Create admin migration user using the below commands:

```
GRANT ALL PRIVILEGES ON *.* TO 'mig_admin'@'%' IDENTIFIED BY 'MIG_ADMIN' WITH GRANT OPTION;  
FLUSH PRIVILEGES;
```
2. Add the below entries in /etc/my.cnf to [mysqld] section and restart MariaDB server to apply the new settings:

```
net_read_timeout=1000  
connect_timeout=1000  
On terminal: systemctl restart mariadb.service
```
3. Using the below command, try connecting to Ubuntu VA using mig_admin user from the new CentOS VA:

```
mysql -umig_admin -pMIG_ADMIN -h<ubuntu VA IP>
```
4. Using the below command, try connecting to CentOS VA from Ubuntu VA:

```
mysql -umig_admin -pMIG_ADMIN -h<Centos VA IP>
```



Note • Make sure both the servers can connect each other, if any issue found in MySQL connection then check /etc/mysql/my.cnf file and comment # bind-address 127.0.0.0 (or) change the bind address to 0.0.0.0.

5. Stop the services, using the below commands:

```
systemctl stop sgdaemon.service  
systemctl stop scandamon.service  
systemctl stop haproxy.service
```
6. Drop the common and private databases (Centos VA) using the below commands:

```
DROP DATABASE ca;  
DROP DATABASE ca_; (Private database starts with ca_)
```
7. Drop the private db mysql users (which starts with customer id) using the below commands:

```
DROP USER '<cust_id*>'@'localhost'  
FLUSH PRIVILEGES;
```

Migration Steps

After successfully creating the admin migration user, follow the below migration steps:



Task

To perform migration steps:

1. In CentOS VA make the following files executable:

```
chmod a+rx /usr/local/Secunia/csi/install/util/migratedb.sh
chmod a+rx /usr/local/Secunia/csi/install/util/dumpPDB.php
```

2. In CentOS VA run the below script:

```
/usr/local/Secunia/csi/install/util/migratedb.sh
```

3. After running the script, you can see a log folder get created at /usr/local/Secunia/csi/install/util/ with the migration successful message. If a log folder is not created then you need to verify the permission of dumpPDB.php, migratedb.sh files. Now run the below script:

```
/usr/local/Secunia/csi/install/util/migratedb.sh
```

4. Script will ask for the below details of source server (Ubuntu) and destination server (CentOS):

```
Source IP
Source MySQL username
Source MySQL password
Destination IP
Destination MySQL username
Destination MySQL password
```

5. Run the below commands for permission and to copy the previously generated reports (pdf and csv):

- **On Ubuntu**—Use the following command:

```
scp /usr/local/Secunia/csi/reports/ root@<centos ip>:/var/spool/On centoscsi/reports/*.*
```

- **On CentOS**—Use the following command:

```
chmod a+rx /usr/local/Secunia/csi/reports
```

6. Start services using the below commands:

```
systemctl start sgdaemon.service
systemctl start scandamon.service
systemctl start haproxy.service
```

7. After migration, remove mysql user - 'mig_admin'@'%' from both the servers using the below commands:

```
DROP USER 'mig_admin'@'%';
FLUSH PRIVILEGES;
```

